

Application Note AN005

Introduction

The SMT100 is a soil moisture sensor capable of measuring soil moisture and soil temperature. The SMT100 is available with a RS485 ASCII interface for easy operation with simple text commands.

RS485 ASCII configuration

The SMT100 ASCII uses these serial port settings:

Baudrate: 9600 Parity: None

Command termination CR, LF or CR+LF

Response termination CR+LF

Seperator between command and address "!" (exclamation mark) or "," (comma)

RS485 ASCII examples

The following communication examples are explained in detail


- Read temperature value from SMT100 sensor via broadcast address 000000
- Read address of SMT100 sensor
- Set address of SMT100 sensor
- Read temperature value from SMT100 sensor via an individual address

Software and Hardware

- Terminalprogram HTerm
- TRUEBNER USB to RS485 interface

1


Read temperature value from SMT100 sensor via broadcast address 000000



• Choose COM Port (e.g. COM25, check device manager for appropriate COM port), set baudrate to 9600 and press connect button.




- Newline at CR+LF
 - Newline at CR+LF
- Send on enter: CR



- Type in command and press enter.
- Important: Connect only 1 sensor to the RS485 interface for this command


2 11/2018

Read address of SMT100 sensor



- Address consists of a maximum of 6 digits
- Important: Connect only 1 sensor to the RS485 interface for this command

Set address of SMT100 sensor




- Address consists of a maximum of 6 digits
- Important: Connect only 1 sensor to the RS485 interface for this command

11/2018

4

Read temperature value from SMT100 sensor via individual address



- Multiple sensors (each with a different address) can be connected to the RS485 bus
- Other commands are
 - ☐ GetWaterContent!address (volumetric water content in %)
 - ☐ GetCounts!address (raw measurement data as number)
 - ☐ GetPermittivity!address (dielectric coefficient)
 - ☐ GetFirmwareVersion!address (firmware version number)